


# Projection Views



## Content

- Coordinate systems
- Orthographic projection
- (Engineering Drawings)



## Graphical Coordinator Systems

A coordinate system is needed to **input**, **store** and **display** model geometry and graphics.

**Four** different types of coordinate systems are used in a CAD system at different stages of geometric modeling and for different tasks.


### Model (or World, Database) Coordinator System

- The **reference space** of the model with respect to which **all** of the geometrical data is stored.
- It is a **Cartesian** system which forms the **default** coordinate system used by a software system.




## Viewing Coordinate System

Textbook setup - for Parallel Projection, the viewer is at infinity.




AutoCAD Default Setup




## Viewing Coordinate System (VCS)


A **3-D Cartesian** coordinate system (right hand or left hand) in which a projection of the modeled object is formed. VSC will be discussed in detail under [Perspective or Parallel Projections](#).







$$\underline{p} = (x \ y \ z)^T$$





$$\underline{p} = (x \ y \ z)^T_{MCS} = (u \ v \ n)^T_{VCS}$$










## Parallel Projection

- Preserve **actual** dimensions and shapes of objects
- Preserve parallelism
- Angles preserved only on faces parallel to the projection plane
- Orthographic projection is one type of parallel projection

## Perspective Projection

- Doesn't preserve parallelism
- Doesn't preserve actual dimensions and angles of objects, therefore shapes deformed
- Popular in **art** (classic painting); architectural design and civil engineering.
- Not commonly used in mechanical engineering





## Geometric Transformations for Generating Projection View

Set Up the Viewing Coordinate System (VCS)

- Define the **view reference point**  $P = (P_x, P_y, P_z)^T$
- Define the **line of the sight vector**  $\vec{n}$  (normalized)  

$$\vec{n} = (N_x, N_y, N_z)^T \text{ and } N_x^2 + N_y^2 + N_z^2 = 1$$
- Define the **"up" direction**  


$$\vec{V} = (V_x, V_y, V_z)^T \perp \vec{n}, \quad \vec{V} \cdot \vec{n} = 0$$

This also defines an orthogonal vector,  $\vec{u} = \vec{V} \times \vec{n}$

$(\vec{u}, \vec{V}, \vec{n})$  forms the **viewing coordinates**

Define the View Window in


$\vec{u} - \vec{v} - \vec{n}$  coordinates



## Generating Parallel Projection

**Problem:** for a given computer model, we know its  $x-y-z$  coordinates in MCS; and we need to find its  $u-v-n$  coordinates in VCS and  $X_s-Y_s$  in WCS.

Getting the  $u-v-n$  coordinates of the objects by transforming the objects and  $u-v-n$  coordinate system together to fully align  $u-v-n$  with  $x-y-z$  axes, then drop the  $n$  (the depth) component to get  $X_s$  and  $Y_s$



## Generating Parallel Projection (1)

First transform coordinates of objects into the  $u-v-n$  coordinates (VCS), then drop the  $n$  component. ( $n$  is the depth)

i.e. Overlapping  $u - v - n$  with  $x - y - z$

i) Translate  $O_v$  to  $O$ .

$$[D] = \begin{bmatrix} 1 & 0 & 0 & -O_{vx} \\ 0 & 1 & 0 & -O_{vy} \\ 0 & 0 & 1 & -O_{vz} \\ 0 & 0 & 0 & 1 \end{bmatrix}$$


ii) Align the  $\bar{n}$  axis with the  $Z$  axis.

The procedure is identical to the transformations used to prepare for the rotation about an axis.

$$A = N_x, \quad B = N_y, \quad C = N_z$$

$$L = \sqrt{N_x^2 + N_y^2 + N_z^2}$$


$$V = \sqrt{N_y^2 + N_z^2}$$



## Generating Parallel Projection (2)

Rotating  $\theta_1$  about X:  $[R]_x$ ; and Rotating  $\theta_2$  about Y:  $[R]_y$

Fully aligning u-v-n with x-y-z




Then, rotate  $\theta_3$  about the Z axis to align  $\bar{u}$  with X and  $\bar{v}$  with Y

## Generating Parallel Projection (3)

Rotate  $\theta_3$  about the Z axis to align  $\bar{u}$  with X and  $\bar{v}$  with Y

At this point,  $\bar{v}$  is given by  $(v'_x, v'_y, 0)^T$  where

$$\begin{pmatrix} v'_x \\ v'_y \\ 0 \\ 1 \end{pmatrix} = [R_y][R_x][D_{O_v,0}] \begin{pmatrix} v_x \\ v_y \\ v_z \\ 1 \end{pmatrix}$$




We need to rotate by an angle  $\theta_3$  about the Z axis

$$L = \sqrt{v'^2_x + v'^2_y}, \quad \sin \theta_3 = \frac{v'_y}{L}, \quad \cos \theta_3 = \frac{v'_x}{L}$$



$$[R_z] = \begin{bmatrix} v'_x/L & -v'_y/L & 0 & 0 \\ v'_y/L & v'_x/L & 0 & 0 \\ 0 & 0 & 1 & 0 \\ 0 & 0 & 0 & 1 \end{bmatrix}$$

Result:



## Generating Parallel Projection (4)


Drop the n coordinate

$$[D_n] = \begin{bmatrix} 1 & 0 & 0 & 0 \\ 0 & 1 & 0 & 0 \\ 0 & 0 & \mathbf{0} & 0 \\ 0 & 0 & 0 & 1 \end{bmatrix}, \quad \begin{pmatrix} u \\ V \\ \mathbf{0} \\ 1 \end{pmatrix} = [D_n] \begin{pmatrix} u \\ V \\ n \\ 1 \end{pmatrix}$$

In summary, to project a view of an object on the UV plane, one needs to transform each point on the object by:


$$[T] = [D_n][R_z][R_y][R_x][D_{o_v,o}]$$

$$\mathbf{P}' = \begin{pmatrix} u \\ V \\ 0 \\ 1 \end{pmatrix} = [T]\mathbf{P} = [T] \begin{pmatrix} x \\ y \\ z \\ 1 \end{pmatrix}$$







**Note:** The inverse transforms are not needed! We don't want to go back to x - y - z coordinates.

## Orthographic Projection




- Projection planes (Viewing planes) are perpendicular to the principal axes of the MCS of the model
- The projection direction (viewing direction) coincides with one of the MCS axes





**Isometric Projection: Equally foreshorten the three main axes**



$$\theta = \pm 45^\circ, \phi = \pm 35.26^\circ$$

### **Other Possible Rotation Paths**

- $R_x \rightarrow R_y$

$$r_x = \pm 45^\circ, r_y = \pm 35.26^\circ$$

- $R_z \rightarrow R_y(R_x)$

$$r_z = \pm 45^\circ, r_{y(x)} = \pm 54.74^\circ$$

- $R_x(R_y) \rightarrow R_z$

$$r_{y(x)} = \pm 45^\circ, r_z = \text{ANY ANGLE}$$